

Wishlist Extension

User Guide

How to configure the extension.

1. Configure the extension.


For installation kindly refer the installation manual.

Once installed kindly browse to, Admin > Stores > Configuration (Settings) > DecryptWeb Extensions > DW Wishlist, below mentioned options will be seen,

Wishlist Feature Actions

- **Enable Wishlist Page Redirect:** If set to 'Yes', the default site behaviour of redirecting the customer to the wishlist page from product detail page (PDP) or product listing page (PLP) on 'Add To Wish List' action would be enabled. The default value is set to 'No' when installed.


Example :



Pic #1

Option Yes For example as seen in the Pic #1 above, If the option is set to 'Yes', on adding the product 'Fusion Backpack' to the wishlist from the product detail page, the customer get's redirected to the wishlist page, this is the default site behaviour.


Option No For example as seen in the Pic #2 below, If the option is set to 'No', on adding the product 'Push It Messenger Bag' to the wishlist from the product detail page, the customer doesn't get redirected to the wishlist page.



Pic #2

- Enable Auto Delete:** If set to 'Yes', the default site behaviour of deleting the wishlist item on adding it to cart from the 'My Wish List' page would be enabled.
 The default value is set to 'No' when installed.

Example :



Pic #3

Option Yes For example as seen in the Pic #3 above, If the option is set to 'Yes', on adding the product 'Fusion Backpack' to the cart from the wishlist page, the product gets deleted from the wishlist page, this is the default site behaviour.

Option No For example as seen in the Pic #4 below, If the option is set to 'No', on adding the product 'Push It Messenger Bag' to the cart from the wishlist page, the product doesn't get deleted from the wishlist page.

Welcome, ▼


LUMA Compare Products (1 item) Search entire store here...

What's New Women Men Gear Training Sale

✓ You added Push It Messenger Bag to your shopping cart.


My Wish List

3 Item(s) Show 10 per page




Push It Messenger Bag
★★★★☆ 3 Reviews
₹45.00

[Add All to Cart](#)



Fusion Backpack
★★★★☆ 3 Reviews
₹59.00




Deirdre Relaxed-Fit Capri
₹63.00

Compare Products (1 item)

Push It Messenger Bag [Compare](#) [Clear All](#)

My Wish List (3 items)



Deirdre Relaxed-Fit Capri X 3 Item(s)
₹63.00

[Add to Cart](#)

Show 10 per page

Pic #4


Welcome, I ▼

LUMA Compare Products (1 item) Search entire store here...

What's New Women Men Gear Training Sale


My Wish List

3 Item(s) Show 10 per page




Push It Messenger Bag
★★★★☆ 3 Reviews
₹45.00

[Update Wish List](#) [Share Wish List](#) [Add All to Cart](#)





Fusion Backpack
★★★★☆ 3 Reviews
₹59.00



Deirdre Relaxed-Fit Capri
₹63.00

Comment


Qty: 1 [Add to Cart](#)

Compare Products (1 item)

Push It Messenger Bag [Compare](#) [Clear All](#)

My Wish List (3 items)




Deirdre Relaxed-Fit Capri X 3 Item(s)
₹63.00

[Add to Cart](#)

Show 10 per page

mag2.loc/index.php/deirdre-relaxed-fit-capri.html?qty=1

Pic #5



Pic #6

Wishlist Page and Item Actions

- **Show Wishlist Item Comment Box:** If set to 'Yes', the default site behaviour of showing the comment box for each wishlist item in 'My Wish List' page would be enabled.

The default value is set to 'No' when installed.

Example :

Option Yes For example as seen in the Pic #5 above, If the option is set to 'Yes', on mouse over the wishlist item 'Deirdre Relaxed-Fit Capri' from the wishlist page, the comment box is seen, its seen for all the wishlist items, this is the default site behaviour.

Option No For example as seen in the Pic #6 above, If the option is set to 'No', on mouse over the wishlist item 'Fusion Backpack' from the wishlist page, the comment box is not seen, it impacts all wishlist items.

- **Show Wishlist Item Edit Icon:** If set to 'Yes', the default site behaviour of showing the edit action icon for each wishlist item in 'My Wish List' page would be enabled for editing the product.

The default value is set to 'No' when installed.

Example :

Option Yes For example as seen in the Pic #5 above, If the option is set to 'Yes', on mouse over the wishlist item 'Deirdre Relaxed-Fit Capri' from the wishlist page, the edit action icon is seen below the quantity box, its seen for all the wishlist items, this is the default site behaviour.

Option No For example as seen in the Pic #6 above, If the option is set to 'No', on mouse over the wishlist item 'Fusion Backpack' from the wishlist page, the edit action icon is not seen below the quantity box, it impacts all wishlist items.

- **Show Wishlist Item Delete Icon:** If set to 'Yes', the default site behaviour of showing the delete action icon for each wishlist item in 'My Wish List' page would be enabled.

The default value is set to 'No' when installed.

Example :

Option Yes For example as seen in the Pic #5 above, If the option is set to 'Yes', on mouse over the wishlist item 'Deirdre Relaxed-Fit Capri' from the wishlist page, the delete action icon is seen below the quantity box, its seen for all the wishlist items, this is the default site behaviour.

Option No For example as seen in the Pic #6 above, If the option is set to 'No', on mouse over the wishlist item 'Fusion Backpack' from the wishlist page, the delete action icon is not seen below the quantity box, it impacts all wishlist items.

- **Show Wishlist Update Button:** If set to 'Yes', the default site behaviour of showing the 'Update Wish List' button in 'My Wish List' page would be enabled. The default value is set to 'No' when installed.

Example :

Option Yes For example as seen in the Pic #5 above, If the option is set to 'Yes', the update button is seen at the botton of wishlist items in the wishlist page, this is the default site behaviour.

Option No For example as seen in the Pic #6 above, If the option is set to 'No', the update button is not seen at the botton of wishlist items in the wishlist page.

- **Show Wishlist Share Button:** If set to 'Yes', the default site behaviour of showing the 'Share Wish List' button in 'My Wish List' page would be enabled. The default value is set to 'No' when installed.


Example :

Option Yes For example as seen in the Pic #5 above, If the option is set to 'Yes', the share button is seen at the botton of wishlist items in the wishlist page, this is the default site behaviour.

Option No For example as seen in the Pic #6 above, If the option is set to 'No', the share button is not seen at the botton of wishlist items in the wishlist page.

2. ACL Configuration

ACL configuration can be found under User Role, under Configuration > Wishlist by DecryptWeb



Pic #7